

KiNET Protocol Tier 1 Specification

Revision Date: December 22, 2009

Revision Control

Date	Revision	Description	Author
30Jul07	E00	Moving to new ESD template and restructuring	B. Chemel
1Aug07	E01	Adding product matrix	B. Chemel
13Aug08	E02	Update Matrix, data sheets, few fixes.	N. Karecki
06Jul09	E03	Adding sync packet	F. Matho
05Nov09	E04	Added PORTOUT flags	J. Warwick



Table of Contents

1	INTRO	DUCTION	4
1.1	En	NDIANNESS AND BYTE ORDERING	4
2	KıNET	·v1	5
2.1	DI	MXOUT PACKET	5
	2.1.1		
	2.1.2	Packet Capture	5
	2.1.3	Field Definitions	5
3	KıNET	v2	8
3.1	PC	ORTOUT PACKET	8
	3.1.1	Packet Diagram	8
	3.1.2	Packet Capture	8
	3.1.3	Field Definitions	8
3.2	2 S	YNC Packet	9
	3.2.1	Packet Diagram	10
	3.2.2	Packet Capture	10
	3.2.3	Field Definitions	

1 Introduction

KiNET is a lightweight UDP/IP based protocol used to communicate via Ethernet with Color Kinetics light fixtures and power supplies. This specification will serve to document the so-called "Tier 1" KiNET functionality; namely, the packet types which encapsulate DMX data, allowing one to send command data to light fixtures.

Two generations of the KiNET protocol have been implemented. These generations will be referred to as "KiNET v1" and "KiNET v2" throughout this document. The following table shows which CK power supplies and data enablers support each version.

Product	KiNET v1 (DMXOUT)	KiNET v2 (PORTOUT)
PDS-150e	Y	N
PDS-500e	Y	N
PDS-60 24V Ethernet	Y	N
PDS-60 24V DMX/Ethernet	Y	Υ
PDS-60ca 12V Ethernet	Y	N
PDS-60ca 7.5V Ethernet	Y	N
PDS-60ca 7.5V DMX/Ethernet	Y	Υ
PDS-70mr 24V Ethernet	Y	N
sPDS-60ca 24V DMX/Ethernet	Υ	Υ
sPDS-480ca (7.5V, 12V, 24V)	N	Υ
Data Enabler Ethernet	Y	N
Data Enabler EO / iColor Accent Powercore	N	Υ

1.1 Endianness and byte ordering

In contrast to the big-endian network byte ordering used by the MAC, UDP, and IP headers, KiNET packets use little-endian byte ordering, with the LSB coming first for all multi-byte fields. See the capture examples below for an illustration (the KiNET header magic number of 0x4ADC0104 is easy to spot).

KiNET v1

2.1 DMXOUT Packet

2.1.1 Packet Diagram

KTYPE_DMXOUT (0x0101)

		Dest	MAC					Source	e MAC			Len	DS			
Tota	l Len	II	ID F Offset				Prot	Heade	r Chks		Sour	ce IP		Dest IP		
Des	st IP	Source Port Dest Port				Len	igth	Chec	ksum		Ma	gic		Version		
Ty	Type Sequence Num				um	Port	Flags	Time	erVal		Univ	Start	Payload			
0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	

2.1.2 Packet Capture

0000	00	0a	C5	22	08	1b	00	12	3f	38	bb	9e	08	00	45	00
0010	02	31	07	<4	00	00	80	11	46	95	0a	01	d5	d6	0a	00
0020	00	8c	0a	8d	17	96	02	1d				01				
0030	01	01	00	00	00	00	00	00	00	00	ff	ff	ff	ff	00	ff
0040	00	00	ff	00	00	00	00	00	00	00	00	00	00	00	00	00
0050	00	00	00	00	00	00	00	00	00	00	00	00	00	00	00	00
0060	00	00	00	00	00	00	00	00	00	00	00	00	00	00	00	00
0070	00	00	00	00	00	00	00	00	00	00	00	00	00	00	00	00

2.1.3 Field Definitions

Note: MAC, IP, and UDP header fields apply for all subsequent KiNET packet types in this document.

2.1.3.1 MAC Header

Field Name	Bytes	Offset	Value	Notes
Dest MAC	6	0		Set to the MAC address of the target power/data supply. Each power/data supply has a unique MAC address that is assigned during manufacture and also marked on the supply via a sticker. The MAC address of a power/data supply can also be determined using the discovery process. For broadcast DMXOUT packet destination MAC should be set to 0xFFFFFFFFFF.
Source MAC	6	6		Set to MAC address of the sender.
Туре	2	12	0x0800	Set to 0x0800 for IP.
Total Size	14			



2.1.3.2 IP Header

Field Name	Bytes	Offset	Value	Notes
Version	4bits	14	0x4	Set to IP version. For KiNET this will always be V4.
Length	4bits	14.5		Set to IP header length, in number of 32-bit words.
DS	1	15	0x00	Set for differentiated services. Not used for KiNET, typically set to 0.
Total Length	2	16		Set to packet total length in bytes, including header and data.
ID	2	18		Set to id for fragmentation. Not used for KiNET.
Flags	4bits	20		Set for fragmentation. KiNET packets will not be fragmented.
Offset	12bits	20.5		Set for fragment offset. Not used for KiNET.
TTL	1	22		Set for time to live. Not used for KiNET.
Protocol	1	23	0x11	Set to UDP (0x11) for KiNET.
Header Checksum	2	24		Set to IP header checksum.
Source IP	4	26		Set to the IP Address of the sender.
Dest IP	4	30		Set to the IP Address of the target power/data supply. Each power/data supply has a unique IP address that is assigned during manufacture and also marked on the supply via a sticker. The IP address of a power/data supply can also be determined using the discovery process. For broadcast DMXOUT packets destination IP should be set to 255.255.255.255.
Total Size	20			

2.1.3.3 UDP Header

Field Name	Bytes	Offset	Value	Notes
Source Port	2	34		Set to source port. User can select an available port (other than 6038) for this use.
Destination Port	2	36	0x1796	Set to 6038 (0x1796). All KiNET packets will use this as dest port.
Length	2	38		Length of UDP header and payload.
Checksum	2	40		Set to checksum of header and data.
Total Size	8			

2.1.3.4 KiNET Header

Field Name	Bytes	Offset	UDP Offset	Value	Notes
Magic Number	4	42	0	0x4ADC0104	
Version	2	46	4	0x0002	Latest version of KiNET protocol is V2.0. Older supplies may support KiNET V1.0 only.
Туре	2	48	6	0x0101	Set to KiNET packet type. For DMXOUT, packet type is 0x0101.
Sequence Number	4	50	8		Can be used for ordering/numbering of packets. Not implemented on most supplies. Should be set to 0.
Total Size	12				

2.1.3.5 KINET DMXOUT Header

Field Name	Bytes	Offset	UDP Offset	Value	Notes
Port	1	54	12	0x00	Not used, set to 0x00.
Flags	1	55	13	0x00	Not used, set to 0x00.
TimerVal	2	56	14	0x0000	Not used, set to 0x0000.
Universe	4	58	16	Oxfffffff	Each power/data supply has a universe setting to facilitate multicast data distribution. The "don't care" value for universe is -1 (0xFFFFFFFF). If a packet is sent with a universe value (other than -1) that does not match that of the supply, the supply will drop the packet.
Total Size	8				

2.1.3.6 KINET DMX Data

Field Name	Bytes	Offset	UDP Offset	Value	Notes
Payload	1- 512	62	20	0x00 then RGB Triples.	Data is sent in RGB triples with one byte per color. Some lights/power supplies also support 16-bit and 12-bit data mode where data will be sent two bytes per color. First byte is DMX start code: 0x00
Total Size	1-512				

KiNET v2

3.1 PORTOUT Packet

3.1.1 Packet Diagram

KTYPE_PORTOUT (0x0108)

	Dest MAC							Sou	rce	MAC	;					Тур	ре	Len	DS	
Total Len	ID	t	TTL Prot Header Chks Sou							Sour	ce IF)		Dest IP						
Dest IP	Source Port		Length Checksum							Magic						Version				
Туре	Sequen		Universe							Port	Pad Flags					Length				
Start Code	Paylo																			
0 1	2 3 4 5				6		7	8		9		10	•	11	1:	2	13	14	15	

3.1.2 Packet Capture

0000	00	Oa	C5	44	15	f2	00	12	3f	38	bb	9e	08	00	45	00
0010	02	34	Of	e7	00	00	80	11	3d	da	0a	01	d5	d6	0a	00
0020	01	21	Oa	8d	17	96	02	20	13	44	04	01	dc	4a	01	00
0030	08	01	00	00	00	00	00	00	00	00	01	00	00	00	00	02
0040	fo	ff	ff	00	00	ff	00									
0050	00	ff	00	00												
0060	ff	00	00	ff												
0070	00	00	ff	00												

3.1.3 Field Definitions

3.1.3.1 KiNET Header

Field Name	Bytes	Offset	UDP Offset	Value	Notes
Magic Number	4	42	0	0x4ADC0104	
Version	2	46	4	0x0002	Latest version of KiNET protocol is V2.0. Older supplies may support KiNET V1.0 only.
Туре	2	48	6	0x0108	Set to KiNET packet type. For PORTOUT, packet type is 0x0108.
Sequence Number	4	50	8		Can be used for ordering/numbering of packets. Not implemented on most supplies. Should be set to 0.
Total Size	12				

3.1.3.2 KINET PORTOUT Header

Field Name	Bytes	Offset	UDP Offset	Value	Notes
Universe	4	54	12	OxFFFFFFF	Each power/data supply has a universe setting to facilitate multicast data distribution. The "don't care" value for universe is -1 (OxFFFFFFFF). If a packet is sent with a universe value (other than -1) that does not match that of the supply, the supply will drop the packet.
Port	1	58	16	0x01 – 0x10	Specifies the port on the supply which the data is going to. Supplies may have anywhere from 1 to 16 ports. It is necessary to send data to each port individually before a sync is sent. Port numbers are indexed starting at 1.
Pad	1	59	17	0x00	Not used, set to 0x00.
Flags	2	60	18	0x00	Bitwise-OR of the following fields:
					0x01 – undefined
					 0x02 – payload format: 0=8 bit data, 1=16 bit data
					 0x04 – data sending: 0=send immediately, 1=hold for SYNC packet
Length	2	62	20		Set to number of bytes in KiNET payload.
Start Code	2	64	22	0x0fff OR 0x0000	Set to 0x0FFF for ChromASIC-based lights. Set to 0x0000 for non-CA lights.
Total Size	12				

3.1.3.3 KINET PORTOUT Data

Field Name	Bytes	Offset	UDP Offset	Value	Notes
Payload	0-512	62	24		Data is sent in RGB triples with one byte per color.
Total Size	0-512				

3.2 SYNC Packet

PORTOUT packets are used to send data to Color Kinetics ChromASIC based products. PORTOUT packets are sent to individual power/data supplies to queue up data for the lights. Typically, supplies will have multiple output ports and the user will send a PORTOUT packet for each port on the supply. Once all of the PORTOUT packets are sent a SYNC packet is sent as a broadcast to tell all supplies to send the queued data to the lights.

3.2.1 Packet Diagram

KTYPE_PORTOUT_SYNC (0x0109)

	Dest MAC					Sourc	e MAC	Туре				Len	DS	
Total Len	ID	F	F Offset		L Prot Header Chks Source			ce IP		Dest IP				
Dest IP	Source Port	De	st Port	Len	gth	Chec	ksum	Magic				Version		
Туре	Sequer	ice Nui	m	Pad										
0 1	2 3	4	5	6	7	8	9	10	11	12	13	14	15	

3.2.2 Packet Capture

0000	ff	ff	ff	ff	ff	ff	00	30	48	92	a1	73	08	00	45	0.0
0010	00	2c	00	00	40	00	40	11	23	ac	0a	07	0d	0f	ff	ff
0020	ff	ff	80	06	17	96	00	18	- 66	bf	04	01	dc	4 a	01	00
0030	09	01	00	00	00	00	00	00	00	00	00	00				

3.2.3 Field Definitions

3.2.3.1 KiNET Header

Field Name	Bytes	Offset	UDP Offset	Value	Notes
Magic Number	4	42	0	0x4ADC0104	
Version	2	46	4	0x0002	Latest version of KiNET protocol is V2.0. Older supplies may support KiNET V1.0 only.
Туре	2	48	6	0x0109	Set to KiNET packet type. For SYNC, packet type is 0x0109.
Sequence Number	4	50	8		Can be used for ordering/numbering of packets. Not implemented on most supplies. Should be set to 0.
Total Size	12				

3.2.3.2 KiNET SYNC Header

Field Name	Bytes	Offset	UDP Offset	Value	Notes
Pad	4	54	12	0x00000000	
Total Size	4				